
# How to set up a POP or IMAP email account in Outlook

Once you've configured and activated your email service, you can set up your POP or IMAP email account in Outlook 2016, Outlook 2019, and Outlook 365.


Below are instructions for configuring your Outlook email settings, whether you prefer to do it automatically or manually for IMAP or POP mail:

## -Automatic account setup-


The first time you open Outlook, you'll encounter a welcome screen like this one:



1. Click Next.



- 2. If you have already set up Outlook before, navigate to the **File tab** located at the top of the window.
- 3. In the **Info** section, click the **Add Account** button.



4. In the **Add an Email Account wizard**, you will be prompted with the question: **"Do you want to set up Outlook to connect to an email account?"** Make sure to select the radio button **"Yes"** then proceed by clicking **Next**.

Add Account X

#### Auto Account Setup

Outlook can automatically configure many email accounts.



● Email Account					
Your Name:	Example: Ellen Adams				
Email Address:	Example: ellen@contoso.com				
Password:					
Retype Password:					
	Type the password your Internet service provid	der has	given you.		
○ Manual setup or additional server types					
			< Back	Next >	Cancel

## 5. In the **Auto Account Setup** panel, enter the following details:

- Your Name: Enter the name you'd like to appear on your emails.
- Email Address: Your full email address.
- **Password**: Your email account password.
- Retype Password: Enter your email account password again.

Add Account

### **Auto Account Setup**

Outlook can automatically configure many email accounts.



Email Account					
Your Name:	Brad Johnson	]			
	Example: Ellen Adams				
Email Address:	brad@myemail.com				
	Example: ellen@contoso.com				
Password:	******				
Retype Password:	******				
	Type the password your Internet service provi	der has give	n you.		
O Manual setup or ac	dditional server types				
			< Back	Next >	Cancel

6. Clicking **Next** will prompt Outlook to retrieve your email server details and proceed with setting up account access.

### -Manual account set up-


- 1. If your server cannot be located, verify that the email address entered is correct and attempt again. Alternatively, you can input your server details manually by choosing "Manual setup or additional server types." Then, proceed by clicking Next.
- 2. Outlook is compatible with various email account types, such as standard POP3/IMAP accounts, Microsoft Exchange or Microsoft 365 accounts, and webmail services like Outlook.com, Hotmail, iCloud, Gmail, Yahoo, among others. For email services offered by your provider, choose **POP or IMAP.**

Add Account


×

POP and IMAP Account Sett Enter the mail server setting			K			
User Information Your Name:		Test Account Settings  We recommend that you test your acc	ount to ensure that			
Email Address:		the entries are correct.				
Incoming mail server:	POP3	Test Account Settings  Automatically test account setting is clicked	ngs when Next			
Outgoing mail server (SMTP):  Logon Information		Deliver new messages to:   New Outlook Data File				
User Name:		Existing Outlook Data File				
Password:			Browse			
✓ Remember password						
Require logon using Secure (SPA)	Password Authentication		More Settings			
		< Back Next >	Cancel			

- 3. Select the radio button next to **POP or IMAP**, then click **Next** to continue configuring your email account. Make sure you have your email server details, username, and password ready for this step.
- 4. Enter the following details:
  - Your Name: Enter the sender's name you'd like to appear on your emails.
  - Email Address: Your full email address.
  - Account Type: Use the dropdown menu to select POP3 or IMAP.
  - **Incoming mail server**: For POP or IMAP accounts, use *mail.yourdomain.tld* if you're on a shared plan (replace yourdomain.tld with your actual domain) or *mail.papamail.net* if you use Basic/Advanced Email services.
  - Outgoing mail server (SMTP): For POP or IMAP accounts,
    use mail.yourdomain.tld if you're on a shared plan (replace yourdomain.tld
    with your actual domain) or mail.papamail.net if you use Basic/Advanced
    Email services.
  - User Name: Your email account username.
  - Password: Your email account password.




5. Click on the "More Settings..." button. Within the Internet Email Settings window, navigate to the Advanced tab.




## 6. Please provide the following information:


- Incoming server: Ensure the default port is set to **995** for POP accounts or **993** for IMAP accounts. Click the checkbox next to **This server requires** an encrypted connection (SSL).
- Outgoing server (SMTP): Change the default port (25) to 465 for POP or IMAP accounts. Use the dropdown menu next to Use the following type of encrypted connection to select SSL.



Switch to the **Outgoing Server** tab. Check the box next to **My outgoing server** (SMTP) requires authentication, then click the button next to **Use same settings** as my incoming mail server.



Click **OK** to close the **Internet E-mail Settings** window. In the **POP and IMAP Account Settings** window, click the **Test Account Settings...** button to ensure Outlook can communicate with your email server.



If the test fails, review your steps and ensure that your server and account details are accurate.

Once the test completes successfully, proceed by clicking **Next**, and then **Finish** to complete the setup.

